

- **save: save the current session commands**

Save aspects of the current state to a command file.

Syntax: **save** <option> <filename>

If no <filename> is given, then the file savexspec.xcm is created. If you don't give the extension to the file name the default is .xcm. The values of <option> allowed are `model`, `files`, and `all`. The `model` option writes out commands to recreate the current model and parameter values; the `files` option writes out commands to read-in the current spectra, and the `all` option does both of the above. The default option is `model`. To recover the saved context use the command

```
XSPEC12>@filename
```

Examples:

```
XSPEC12> save model fname
```

```
// Write out model commands to the file fname.xcm
```

```
XSPEC12> save
```

```
// Same as above, but save into file savexspec.xcm.
```

```
XSPEC12> save files fname
```

```
// Write out data file commands.
```